

SONARWIZ

Function	Shortcut Key(s)	Restrictions
Pan	CTRL+A	
Create survey line to selected contact	SHIFT+CTRL+A	Data acquisition only
Bottom track selected file	CTRL+B	
Import bathymetry files	CTRL+ALT+B	
Open map manager	SHIFT+CTRL+B	
Send selected sonar file to back	SHIFT+B	
Send selected sonar file to backward	ALT+B	
Center plan view on mouse position	C	
Copy selected survey line to clipboard	CTRL+C	Data acquisition only
Copy selected survey lines to clipboard	CTRL+C	Data acquisition only
Open digitizer view on selected sonar file	CTRL+D	
Increase real-time bottom tracker offset	CTRL+E	Data acquisition only
Decrease real-time bottom tracker offset	SHIFT+CTRL+E	Data acquisition only
Resize the view to contain all sonar data	CTRL+F	
Resize the view to contain all data	SHIFT+CTRL+F	
Bring selected sonar file to front	SHIFT+F	
Bring selected sonar file forward	ALT+F	
Toggle plan view X/Y grid overlay	CTRL+G	
Toggle plan view geodetic grid overlay	ALT+G	
Import sidescan files	CTRL+I	
Import magnetometer files	CTRL+ALT+I	
Import sub-bottom files	SHIFT+CTRL+I	
Jump to entered coordinates	J	
Toggle display of left/right steering indicator	ALT+L	Data acquisition only
Set the mouse to measure mode	CTRL+M	
Toggle plan view display of map scale	SHIFT+CTRL+M	
Generate bathymetric pyramids for plan view	SHIFT+M	Bathymetry only
Select next survey line for steering	SHIFT+N	Data acquisition only
Open an existing SonarWiz project	CTRL+O	
Open the thermal printer setup window	CTRL+P	Data acquisition only
Select previous survey line for steering	SHIFT+P	
Abort a lengthy drawing operation	CTRL+Q	
Redraw the plan view	CTRL+R	
Reverse the selected survey line	ALT+R	Data acquisition only
Save the current project	CTRL+S	
Paste the copied survey line	CTRL+V	
Open Vessel Editor	ALT+V	

SONARWIZ

Zoom the plan view to the selected file	Z	
Undo (where available)	ALT+BACK	
Cut selected survey lines	SHIFT+DELETE	Data acquisition only
Open user guide as PDF file	F1	
Open project setup window	F10	
Open existing SonarWiz project	CTRL+F10	
Open sonar file manager window	F11	
Open survey line manager window	F12	Data acquisition only
Configure sonar layback settings	F2	Data acquisition only
Stop recording	F4	Data acquisition only
Start recording	F5	Data acquisition only
Add event mark while recording	F7	Data acquisition only
Open the digitized feature manager window	F8	
Open the contact manager window	SHIFT+F8	
Capture the plan view window to the clipboard	F9	
Toggle the auto ship centering mode	CTRL+HOME	Data acquisition only
Copy selected survey lines to clipboard	CTRL+INSERT	Data acquisition only
Paste clipboard survey lines to plan view	SHIFT+INSERT	Data acquisition only
Zoom in by 10 percent	NEXT	
Zoom out by 10 percent	PRIOR	
Open the map corrections window	CTRL+SPACE	
Set the plan view cursor in swipe mode	SHIFT+CTRL+W	
Cut selected survey lines to clipboard	CTRL+X	Data acquisition only
Redo (where available)	CTRL+Y	
Undo (where available)	CTRL+Z	
Set the plan view cursor in rectangle zoom mode	SHIFT+Z	